


# Editing Fujitsu Data e- TRUST Account Information

Fujitsu Limited




| Version | Date              | Reason for change  |
|---------|-------------------|--|
| 1.0     | August 31, 2023   | First version  |
| 1.1     | September 7, 2023 | English edits  |
| 1.2     | November 10, 2023 | The use of underscores(_) has been prohibited for Agent IDs.             |
| 1.3     | March 22, 2024    | Revise the technology name from “Data e-TRUST” to “Fujitsu Data e-TRUST” |


- This document explains how to edit account information for Fujitsu Data e-TRUST.
  - By following these steps, users will be able to set the attributes used for Fujitsu Data e-TRUST (ID and role) for the API access token.
  - For details about the attributes used for Fujitsu Data e-TRUST, please refer to the text below.
    - "2.2 On Roles in Fujitsu Data e-TRUST" in the Fujitsu Data e-TRUST Features Manual

#### Notes

The contents of this manual may differ from the latest version.

- On the Fujitsu Data e-TRUST "Details" page, click the "Fujitsu Data e-TRUST attributes" button to go to the "Authentication" page.





**FUJITSU**


Fujitsu Research Portal

username/email address

Password

Sign in

- Sign in from the "Authentication" page
  - After signing in you will be redirected to the "Edit Profile" page



← Cancel

**FUJITSU**

### Edit Profile

User Role for Fujitsu Data e-TRUST\*

user

User ID

Agent1 Role for Fujitsu Data e-TRUST

- admin
- user
- tseal admin
- tseal agent
- tseal user

sandbox001

- On the "Edit Profile" page, enter the following settings
  - User Role for Fujitsu Data e-TRUST
    - Both "User Role" and "User ID" are required fields
    - The User ID default value is the account's Object ID
    - The User ID should be within 100 characters and can include letters, numbers, underscores (\_), hyphens (-), @, and periods (.). Text strings starting with \_system\_ or \_trust\_ are not allowed.
  - Agent1 Role for Fujitsu Data e-TRUST
    - Select the appropriate role from admin/user/tseal admin/tseal agent/tseal user
    - Set roles for Agent 1 to Agent 10 in the same way
    - The default values for Agent1 - Agent4 are as follows:
      - Role: admin and tseal user
      - ID: sandbox001 - sandbox004
    - The ID should be within 50 characters and can include letters, numbers and hyphens (-). Character strings contain underscore (\_) are not allowed.
- When the settings are complete, click the "Continue" button at the bottom of the page.
  - The edit process is now complete
  - The edit screen will close automatically



**Thank you**

